

AutoCAD LT 2009

Stand-Alone Installation Guide

The Autodesk logo is displayed in white text on a black rectangular background. The text is oriented vertically, reading from bottom to top.

January 2008

© 2008 Autodesk, Inc. All Rights Reserved. Except as otherwise permitted by Autodesk, Inc., this publication, or parts thereof, may not be reproduced in any form, by any method, for any purpose.

Certain materials included in this publication are reprinted with the permission of the copyright holder.

Trademarks

The following are registered trademarks or trademarks of Autodesk, Inc., in the USA and other countries: 3DEC (design/logo), 3December, 3December.com, 3ds Max, ActiveShapes, Actrix, ADI, Alias, Alias (swirl design/logo), AliasStudio, AliasWavefront (design/logo), ATC, AUGI, AutoCAD, AutoCAD Learning Assistance, AutoCAD LT, AutoCAD Simulator, AutoCAD SQL Extension, AutoCAD SQL Interface, Autodesk, Autodesk Envision, Autodesk Insight, Autodesk Intent, Autodesk Inventor, Autodesk Map, Autodesk MapGuide, Autodesk Streamline, AutoLISP, AutoSnap, AutoSketch, AutoTrack, Backdraft, Built with ObjectARX (logo), Burn, Buzzsaw, CAiCE, Can You Imagine, Character Studio, Cinestream, Civil 3D, Cleaner, Cleaner Central, ClearScale, Colour Warper, Combustion, Communication Specification, Constructware, Content Explorer, Create>what's>Next> (design/logo), Dancing Baby (image), DesignCenter, Design Doctor, Designer's Toolkit, DesignKids, DesignProf, DesignServer, DesignStudio, DesignStudio (design/logo), Design Your World, Design Your World (design/logo), DWF, DWG, DWG (logo), DWG TrueConvert, DWG TrueView, DXF, EditDV, Education by Design, Exposure, Extending the Design Team, FBX, Filmbox, FMDesktop, Freewheel, GDX Driver, Gmax, Heads-up Design, Heidi, HOOPS, HumanIK, i-drop, iMOUT, Incinerator, IntroDV, Inventor, Inventor LT, Kaydara, Kaydara (design/logo), LocationLogic, Lustre, Maya, Mechanical Desktop, MotionBuilder, Mudbox, NavisWorks, ObjectARX, ObjectDBX, Open Reality, Opticore, Opticore Opus, PolarSnap, PortfolioWall, Powered with Autodesk Technology, Productstream, ProjectPoint, ProMaterials, Reactor, RealDWG, Real-time Roto, Recognize, Render Queue, Reveal, Revit, Showcase, ShowMotion, SketchBook, SteeringWheels, StudioTools, Topobase, Toxik, ViewCube, Visual, Visual Bridge, Visual Construction, Visual Drainage, Visual Hydro, Visual Landscape, Visual Roads, Visual Survey, Visual Syllabus, Visual Toolbox, Visual Tugboat, Visual LISP, Voice Reality, Volo, Wiretap, and WiretapCentral

The following are registered trademarks or trademarks of Autodesk Canada Co. in the USA and/or Canada and other countries: Backburner, Discreet, Fire, Flame, Flint, Frost, Inferno, Multi-Master Editing, River, Smoke, Sparks, Stone, and Wire

All other brand names, product names or trademarks belong to their respective holders.

Disclaimer

THIS PUBLICATION AND THE INFORMATION CONTAINED HEREIN IS MADE AVAILABLE BY AUTODESK, INC. "AS IS." AUTODESK, INC. DISCLAIMS ALL WARRANTIES, EITHER EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE REGARDING THESE MATERIALS.

Published by:
Autodesk, Inc.
111 McInnis Parkway
San Rafael, CA 94903, USA

Contents

Chapter 1	Quick Start to Stand-Alone Installation	1
	How to Prepare for Installation	1
	How to Review System Requirements	1
	How to Understand Administrative Permission Requirements	2
	How to Install Multiple or Bundled Products	2
	How to Locate Your AutoCAD LT 2009 Serial Number	2
	How to Avoid Data Loss During Installation	3
	How to Migrate Custom Settings from Previous Versions	3
	How to Install and Run AutoCAD LT	3
	How to Install AutoCAD LT	3
	How to Register and Activate AutoCAD LT	4
	How to Launch AutoCAD LT 2009	4
	How to Install and Start the CAD Manager Control Utility	5
	How to install the CAD Manager Control utility	5
Chapter 2	Move to AutoCAD LT 2009 from a Previous or Same Release	7
	Migrate Custom Settings and Files from Previous Releases	7
	Migrate Custom Settings	8
	View the Migration Log File	12
	Use Migration Tools	12
	Export and Import Custom Settings from the Same Release	13

Export Custom Settings	15
Import Custom Settings	16
Locate Customized Files	17
Locate Plot Style Files	18
Locate Plotter Files	18
Locate the PMP File	19
Locate Support Files	20
Locate Drawing Template Files	22
Chapter 3 Install Autodesk Products for an Individual User	25
The AutoCAD LT 2009 Installation Wizard	25
System Requirements	26
Install AutoCAD LT	28
Register and Activate AutoCAD LT	31
Add or Remove Features	32
Reinstall or Repair AutoCAD LT	33
Uninstall AutoCAD LT	34
Features that Require Design Review	35
Chapter 4 Installation Troubleshooting	37
General Installation Issues	37
How can I check my graphics card driver to see if it needs to be updated?	37
What is the text editor used for?	38
When performing a Typical installation, what gets installed?	38
Where are my product manuals?	39
Deployment Issues	39
Is there a checklist I can refer to when performing a deployment?	39
Where should deployments be located?	39
Where can I check if service packs are available for my software?	40
How do I extract an MSP file?	40
Can Online Resource settings be modified later?	40
Where can I learn about InfoCenter?	41
What are information channels?	41
What are the benefits to enabling CAD Manager Channels?	41
What are RSS feeds and how do they benefit my installation?	42
Where can I learn about InfoCenter search locations?	42
How do I set or customize search locations?	42
Licensing Issues	42

What is the difference between a stand-alone license and a network license?	43
What is the benefit to using a network licensed version of the software?	43
What is Internet Explorer used for?	43
Networking Issues	44
When installing tools and utilities, which selections are applicable for a multi-seat stand-alone installation?	44
When installing tools and utilities, which selections are applicable for a stand-alone installation?	44
If I choose to create a log file, what kind of information does the log file contain?	44
When specifying user workstation settings, I'm given the option to specify a profile. What are profiles?	45
Can I create custom desktop shortcuts?	45
What happens when you choose to append or merge service packs?	45
What is an administrative image (MSI) file?	46
What is the impact of selecting all products to be included in the administrative image?	46
Uninstall and Maintenance Issues	46
When adding or removing features, how can I tell what features get installed by default?	47
Is it possible to change the installation folder when adding or removing features?	47
When should I reinstall the product instead of a repair?	48
Do I need my original disk to reinstall my software?	48
After repairing my installation, is it possible to recover my settings?	48
When I uninstall my software, what files are left on my system?	48
Index	49

Quick Start to Stand-Alone Installation



This section provides step-by-step instructions about how to install AutoCAD LT on your system. You should read the entire *Stand-Alone Installation Guide* if you have any questions that are not addressed in this Quick Start section.

For information about installing network-licensed or multi-seat stand-alone versions of the program, see the Network Administrator's Guide.

How to Prepare for Installation

Before you install AutoCAD LT, you need to review the system requirements, understand administrative permission requirements, locate your AutoCAD LT 2009 serial number, and close all running applications. After you complete these tasks, you can install AutoCAD LT.

How to Review System Requirements

Make sure that the computer on which you install AutoCAD LT meets the system requirements. If your system does not meet the system requirements, many problems can occur, both within AutoCAD LT and at the operating system level.

To review the system requirements, see System Requirements on page 26.

How to Understand Administrative Permission Requirements

To install AutoCAD LT, you must have administrator permissions. You do not need to have domain administrative permissions. See your system administrator for information about administrative permissions.

To run AutoCAD LT, you do not need administrator permissions. You can run the program as a limited user.

How to Install Multiple or Bundled Products

Some Autodesk packages are comprised of multiple products or are part of *multi-product bundles*.

In the Installation wizard for packages containing multiple products, you can choose which products you want to install. During the install process, you are informed whether a copy of the software is already installed, you are also warned if your system does not meet the minimum system requirements for the product. Each product name is displayed on its own tabbed panel; you can configure them individually.

If you purchased a package that is a multi-product bundle, such as an educational or institutional package, you may have a package that includes several Autodesk products. For these bundled packages, an Installer Disk contains information for all the products in the package. The Installer Disk helps you install all of the products.

How to Locate Your AutoCAD LT 2009 Serial Number

When you activate AutoCAD LT, you are prompted for your serial number. Your serial number is located on the outside of the product package. Make sure to have this number available before you activate the program so that you don't have to stop in the middle of the installation.

How to Avoid Data Loss During Installation

The AutoCAD LT installation process may stop if some applications (such as Microsoft® Outlook® or virus-checking programs) are running. Close all running applications to avoid possible data loss.

How to Migrate Custom Settings from Previous Versions

You can migrate your custom settings and files from previous releases of AutoCAD LT (AutoCAD LT 2000 through AutoCAD LT 2009) to AutoCAD LT 2009. It is recommended that you migrate from a previous release when you first use AutoCAD LT 2009 or soon thereafter. Migrating right away prevents you from overwriting files or having to keep track of any custom settings you may make in the new release.

For more details regarding migration, see Migrate Custom Settings and Files from Previous Releases on page 7.

How to Install and Run AutoCAD LT

To use the product, you must install the product, register and activate it, and then launch it.

How to Install AutoCAD LT

- 1 Insert the AutoCAD LT DVD, or the first CD, into your computer's drive.
- 2 In the AutoCAD LT Installation wizard, click Install Products.
- 3 Follow the directions on each installation page.

If installing from CDs, insert the remaining AutoCAD LT CDs when prompted, to complete the installation.

NOTE When you select Install without making any changes, the Installation wizard asks you to confirm you want to continue installing using the default configuration. If you select Yes, a Typical installation takes place. For more information, see Install AutoCAD LT on page 28

How to Register and Activate AutoCAD LT

After AutoCAD LT is installed, you can initiate the registration process by launching the product. When you launch AutoCAD LT, the Product Activation wizard is displayed. Follow the directions in the Product Activation wizard to register the product.

Make sure you have your product serial number available. You cannot register and activate AutoCAD LT without it.

NOTE If you are upgrading from an earlier release of AutoCAD LT, use your new serial number when you register and activate the new release.

For more information about registering AutoCAD LT, see Register and Activate AutoCAD LT on page 31.

How to Launch AutoCAD LT 2009

Assuming that you followed all of the previous steps outlined in this Quick Start section, you can launch AutoCAD LT and start taking advantage of its new and updated features. For more information about the new features, see the New Features Workshop after you launch the product.

You can start AutoCAD LT in the following ways:

- **Desktop shortcut icon.** When you install AutoCAD LT, an AutoCAD LT 2009 shortcut icon is placed on your desktop unless you cleared that option during installation. Double-click the AutoCAD LT 2009 icon to start AutoCAD LT.
- **Start menu.** On the Start menu (Windows), click All Programs (or Programs) ► Autodesk ► AutoCAD LT 2009 ► AutoCAD LT 2009.
- **Location where AutoCAD LT is installed.** If you have administrative permissions, you can run AutoCAD LT in the location where you installed it. If you are a limited-rights user, you must run AutoCAD LT from the Start menu or from the desktop shortcut icon. If you want to create a custom shortcut, make sure that the Start In directory for the shortcut points to a directory where you have write permissions.

How to Install and Start the CAD Manager Control Utility

Using the Autodesk CAD Manager Control utility, CAD managers can selectively control which users have access to Internet-based content and information from DesignCenter Online, Communication Center, and the Subscription Center. They can also determine if users receive notification when reported errors are resolved.


How to install the CAD Manager Control utility

- 1 Insert the product DVD, or the first CD, into your computer's drive.
- 2 In the Installation wizard, click Install Tools and Utilities.
- 3 On the Select the Products to Install page, select Autodesk CAD Manager Tools, click Next.
- 4 Review the Autodesk software license agreement for your country or region. You must accept this agreement to proceed with the installation. Select your country or region, click I Accept, and then click Next.

NOTE If you do not agree to the terms of the license and want to terminate the installation, click Cancel.

- 5 On the Review - Configure - Install page, click Install if you want to accept the default install location.

When you select Install without making any changes, the Installation wizard asks you to reconfirm you want to continue installing using the default configuration.



If you want the utility installed in a different installation path, click Configure, set the path, click Configuration Complete and then Install.

- 6 When the Installation Complete page is displayed, click Finish.

How to start the CAD Manager Control utility

- 1 On the Start menu (Windows), click All Programs (or Programs) ► Autodesk ► CAD Manager Tools ► CAD Manager Control Utility.
- 2 Select the product you want to modify. Click OK.

Move to AutoCAD LT 2009 from a Previous or Same Release

2

If you have a previous version of AutoCAD LT installed on your system, you can install AutoCAD LT 2009 and keep other versions of the program on the same system. This is called a *side-by-side* installation. If you've purchased an *upgrade* version of AutoCAD LT, you are required to uninstall the previous version within 120 days of installing AutoCAD LT 2009. See your license agreement for more information.

In this section, you learn about migrating from previous releases, using customized files from previous releases, and locating customized files.

Migrate Custom Settings and Files from Previous Releases

You can migrate your custom settings and files from previous releases of AutoCAD LT (AutoCAD 2000 through AutoCAD LT) to AutoCAD LT 2009. It is recommended that you migrate from a previous release when you first use AutoCAD LT 2009 or soon thereafter. Migrating right away prevents you from overwriting files or having to keep track of any custom settings you may make in the new release.

You can use the following tools to migrate settings and files:

- **Migrate Custom Settings dialog box.** Migrates user profiles, CUI files, AutoCAD LT and user-defined linetype files, AutoCAD LT and user-defined hatch patterns, and the *acadlt.pgp* file (a file that stores command definitions and aliases). The Migrate Custom Settings dialog box is displayed when you

start AutoCAD LT for the first time. You can also migrate settings later from the Start menu (Windows).

- **Customize User Interface dialog box.** Converts legacy menu files (MNU and MNS) to the CUI format while leaving the original MNU or MNS file unchanged. Migrating user interface elements, transferring data between customized files, and customizing user interface elements are simplified in this dialog box. For more information about the CUI format and how migration of menu files has been simplified, see *Customize the User Interface* in the *Customization Guide*.
- **Migration tools.** Aid migration of settings or files that cannot be automatically migrated (such as AutoLISP® files and the accompanying MNL files) or that require you to make a decision about which files to migrate (such as which files in a set of drawing files). Download these migration tools by visiting www.autodesk.com and then performing a search on Migration Tools.

NOTE For information about customizing files and settings, see the *Customization Guide*, accessible from the Documentation link on the AutoCAD LT 2009 Installation wizard and in the Help system.

Migrate Custom Settings

If you install AutoCAD LT 2009 on a computer where a previous release of AutoCAD LT (AutoCAD 2000 through AutoCAD LT) is installed, you can migrate some custom settings from a previous release to AutoCAD LT 2009.

Migrate linetypes, hatch patterns, and command aliases that you created. The data from these files is added to a user-defined section of the AutoCAD LT 2009 files, to make it easy for you to find this information and migrate this data to future releases. You cannot use the Migrate Custom Settings dialog box to migrate shell commands or comments that you made to your *acadlt.pgp* file.

NOTE If you have made changes to partial plotter configuration (PC3) files that are located in a custom folder, those files are migrated to the *AutoCAD LT 2009 PC3* folder, which is located under your custom *PC3* folder. PC3 files are migrated to a separate folder to maintain backward compatibility with previous AutoCAD LT releases.

The following table lists the files that are migrated with the Migrate Custom Settings dialog box, a description of each file, and file details to help you decide if you want to migrate a file.

Files Migrated with the Migrate Custom Settings Dialog Box

File Name	File Description	Details
<i>*.lin</i>	Stores your user-defined linetypes.	User-defined linetype files are migrated.
<i>acadlt.lin</i>	Contains standard linetype definitions (an AutoCAD LT library file).	The file itself is not migrated; however, any linetypes that you created in this file are migrated to the AutoCAD LT 2009 <i>acadlt.lin</i> file, in the <i>User Defined Linetypes</i> section of the file.
<i>acadltiso.lin</i>	Contains metric linetype definitions (an AutoCAD LT library file).	The file itself is not migrated; however, any linetypes that you created in this file are migrated to the AutoCAD LT 2009 <i>acadltiso.lin</i> file, in the <i>User Defined Linetypes</i> section of the file.
<i>*.pat</i>	Stores user-defined hatch patterns.	User-defined hatch pattern files are migrated.
<i>acadlt.pat</i>	Contains standard hatch pattern definitions (an AutoCAD LT library file).	The file itself is not migrated; however, any hatch patterns that you created in this file are copied to the AutoCAD LT 2009 <i>acadlt.pat</i> file, in the <i>User Defined Hatch Patterns</i> section of the file.
<i>acadltiso.pat</i>	Contains metric hatch pattern definitions (an AutoCAD LT library file).	The file itself is not migrated; however, any metric hatch patterns that you created in this file are copied to the AutoCAD LT 2009 <i>acadltiso.pat</i> file, in the <i>User Defined Hatch Patterns</i> section of the file.

Files Migrated with the Migrate Custom Settings Dialog Box

File Name	File Description	Details
<i>acadlt.pgp</i>	Stores shell commands and command alias definitions (a program parameters file in ASCII text form).	The file itself is not migrated; however, any command aliases you created in this file are copied to the AutoCAD LT 2009 <i>acadlt.pgp</i> file.
*.mnu	Contains menu customization from a version of AutoCAD LT earlier than AutoCAD LT 2006.	The file itself is not migrated; however, a copy of the file is created and then is converted into a CUI file with the same name. The new CUI file is placed in the same folder as the main CUI file. A MNU file is converted when a MNS file with the same name is not found.
*.mns	Contains menu customization from a version of AutoCAD LT earlier than AutoCAD LT 2006.	The file itself is not migrated; however, a copy of the file is created and then is converted into a CUI file with the same name. The new CUI file is placed in the same folder as the main CUI file. A MNS file is converted when a MNU file with the same name is present or not.
*.cui	Contains customizations from a version of AutoCAD LT starting with AutoCAD LT 2006.	If the CUI file is supplied by Autodesk, the custom changes made to the file are migrated to the newer version of the CUI file. If the CUI file is not supplied by Autodesk, the file is migrated and is copied to where the main CUI file is located, unless the CUI file is in a network location. In that case, the file is migrated but is not copied to the location of the main CUI file. Enterprise CUI files are not migrated automatically. You must migrate them manually.

Before the MNU, MNS, and CUI files are migrated, a backup copy of each file is saved in the following directory:

\Documents and Settings\<<user profile>\Application Data\Autodesk\<<product version>\<release number>\<language>\Previous Version Custom Files

NOTE Other custom settings and files can be migrated using Autodesk migration tools. For more information about migration tools, see *Use Migration Tools* on page 12.

To migrate custom settings when you start AutoCAD LT 2009

- 1 Start AutoCAD LT 2009.
- 2 In the Migrate Custom Settings dialog box, in the Migrate Settings From list, select the AutoCAD LT release from which you want to migrate your custom settings.
- 3 In the Settings and Files to Migrate box, select the custom files that you want to migrate.
- 4 Click OK.
- 5 In the Migrate Custom Settings message, click OK to view the log file, or click No if you do not want to view the log file now.

NOTE You can view the log file at another time. For information about accessing the log file at another time, see *View the Migration Log File* on page 12.

Each time the Migrate Custom Settings dialog box is used, AutoCAD LT resets the program's default CUI file from the *UserDataCache* folder and then migrates any customization done in a previous release forward.

To migrate custom settings from the Start menu (Windows)

- 1 Click Start menu (Windows) ► All Programs (or Programs) ► Autodesk ► AutoCAD LT 2009 ► Migrate Custom Settings ► Migrate From a Previous Release.
- 2 In the Migrate Custom Settings dialog box, in the Migrate Settings From list, select the AutoCAD LT release from which you want to migrate your custom settings.
- 3 In the Settings and Files to Migrate box, select the custom files that you want to migrate.

- 4 Click OK.
- 5 In the Migrate Custom Settings message, click OK to view the log file, or click No if you do not want to view the log file.

NOTE To be accessible, pull-down menus that are migrated from a MNU/MNS file to a CUI file need to be added to a workspace.

View the Migration Log File

The migration log file (*migration.xml*) provides specific information about any settings or files that were not successfully migrated to AutoCAD LT 2009. The log file shows all the files that were successfully copied from a previous version to AutoCAD LT 2009. It also provides information about files that were not successfully migrated. Use the log for troubleshooting if there are unwanted or unexpected results in your AutoCAD LT 2009 profiles.

After you use the Migrate Custom Settings dialog box to migrate custom settings and files, a message is displayed from which you open the migration log file. You can view the migration log file at that time. You can also navigate to the file if you want to view the log details another time.

To locate and view the migration log file

- 1 In Windows Explorer, navigate to the following location:
`\Documents and Settings\<user profile>\Application Data\Autodesk\<product version>\<release number>\<language>\Migration.`
- 2 Double-click *migration.xml* to open the file, and view the details of your migration.

Use Migration Tools

Migration tools take the guesswork out of updating your custom files from previous releases. The tools help you to share drawings when you upgrade to a new release of AutoCAD LT. You can download the migration tools in several languages from the Autodesk website.

NOTE Because these are public tools, product support for them is limited to the Autodesk discussion groups.

The migration tools are as follows:

- **DWG TrueView 2009.** You can view, plot, and convert any AutoCAD LT or AutoCAD LT-based drawing file for compatibility with AutoCAD Release 14, AutoCAD 2000, AutoCAD 2004, and AutoCAD 2007 drawing file formats.

Export and Import Custom Settings from the Same Release

You can export your custom settings between systems running the same release of AutoCAD LT, or export the custom settings and later re-import them on the same computer if you need to reinstall AutoCAD LT. When exporting custom settings, a migration package is created that contains an XML file. This file contains custom settings, a listing of the custom files from local locations used with AutoCAD LT, and optionally, custom files in network locations.

The migration package is a ZIP file archive, so it has the file extension ZIP. During the import process, you select the ZIP file archive that contains the exported custom settings you want to merge onto your computer.

The following table lists the file types that are most commonly included in the migration package that is created from the Export Custom Settings dialog box.

Most Common File Types Included in the Migration Package

File Name	File Description
<i>*.xml</i>	Information about the user profiles in the product and the original locations of the files in the export package.
<i>*.lin</i>	Linetype definitions.
<i>*.pat</i>	Hatch pattern definitions.
<i>*.pgp</i>	Shell commands and command alias definitions.
<i>*.pc3</i>	Configuration information for a plotter or printer.

Most Common File Types Included in the Migration Package

File Name	File Description
<i>*.pmp</i>	Calibration and paper size settings that are used with a PC3 file.
<i>*.ini</i>	Configuration settings for some features.
<i>*.shx</i>	Information about text characters or shapes used with linetype definitions.
<i>*.ctb</i>	Settings used to control the appearance of objects when plotting; the settings are arranged by the colors of the AutoCAD Color Index (ACI) system.
<i>*.stb</i>	Settings used to control the appearance of objects when plotting; the settings are grouped into names that can be assigned to a layer or object.
<i>*.cui</i>	Information for commands and user interface elements.
<i>*.fmp</i>	Information about font mappings for True Type Fonts used in the In-place Text Editor.
<i>*.cus</i>	Custom dictionary entries.
<i>*.bmp</i>	Image used for a command in a customization file.
<i>*.atc</i>	Tools defined on a tool palette and the tool palette catalog. The file is not migrated from release to release, but is from computer to computer with the migration package.
<i>*.aws</i>	Order of the tools as they appear on a tool palette and other local settings. The file is not migrated from release to release, but is from computer to computer with the migration package.

The following table lists the file types that are not included in the migration package that is created from the Export Custom Settings dialog box.

Some of the File Types Not Included in the Migration Package

File Name	File Description
*.mnr	Resource images for a customization file; must have the same name as a customization file in order to be loaded by the product. The file is not included because it is auto-generated by the product when it is not present.
*.unt	Unit definitions used for converting a value from one unit type to another.

NOTE For information about customizing files and settings, see the *Customization Guide*, accessible from the Documentation link on the AutoCAD LT 2009 Installation wizard and in the Help system.

Export Custom Settings


When exporting custom settings, the custom files stored locally and all user profiles are exported to a migration package. You have the option to include custom files that are stored in network locations. During the creation of the migration package, you do not have any control over which types of files are included in the migration package.

The Export Custom Settings dialog box is used to create the migration package so it can be imported to another computer or the same computer running the same release of the product.

NOTE You must launch AutoCAD LT at least once before you can export custom settings to a migration package.

To export custom settings

- 1 Click Start menu (Windows) ► All Programs (or Programs) ► Autodesk ► AutoCAD LT 2009 ► Migrate Custom Settings ► Export AutoCAD LT 2009 Settings.
- 2 In the Export Custom Settings dialog box, select the Include Custom Files in Networked Locations option if you have files in network locations that you want included in the migration package that is created.



- 3 Click Export.
- 4 In the Export Custom Settings file navigation dialog box, enter a name and specify a location for the migration. Click Open.
A new ZIP file is created.
- 5 In the confirmation message box, click OK.

Import Custom Settings

By importing a migration package, you can configure AutoCAD LT in the same way as other computers that are running the same release of the product. Upon the successful import of the migration package, a message box is displayed giving you the option of viewing the migration log that is created. If any errors are encountered during the import process, they are logged in the migration log.

If files from a network location were added during the creation of a migration package, the files are copied to a different location only when the original network locations are not available when importing a migration package. If the files from a network location are found in the same location on the network, the files are not copied to the network location and are ignored during import.

Local paths that exist as part of a user profile in a migration package are created automatically during the import process, but paths that are on a network drive or a drive that uses removable media are not created automatically.

NOTE You must launch AutoCAD LT at least once before you can import a migration package.

To import custom settings from a computer with the same release of AutoCAD LT

- 1 Click Start menu (Windows) ► All Programs (or Programs) ► Autodesk ► AutoCAD LT 2009 ► Migrate Custom Settings ► Import AutoCAD LT 2009 Settings.
- 2 In the Import Custom Settings file navigation dialog box, select the ZIP file that contains the custom settings that were exported. Click Open.
- 3 On the AutoCAD LT 2009 message box, click OK.
Optionally, select the Display Log File After Closing This Dialog option before clicking OK to display the log file that was created during the importing of the migration package.

To view the migration log after custom settings imported

- 1 In Windows Explorer, navigate to the following location:
`\Documents and Settings\<user profile>\Application Data\Autodesk\<product version>\<release number>\<language>\Migration.`
- 2 Double-click *migration.xml* to open the file and view the details of your migration.

Locate Customized Files

Beginning with AutoCAD LT 2004, the location of some of your customized files has changed. The reasons for the file location changes include the following:

- Limited user rights on a workstation. You can run AutoCAD LT as a limited user. This means that you no longer need power user or Administrator permissions to run AutoCAD LT once it is installed.
- Roaming profiles. Roaming profiles allow you to log on to any computer within a network and retain your user settings. Some files, such as your personal settings and documents, follow you from computer to computer, while other files, such as templates (including Publish to Web templates), reside only on your system.
If roaming profiles are allowed on your network, your “roamable” files are located in the `\Application Data\Autodesk\<Product Version>` folder, and your “nonroamable” files are located in the `\Local Settings\Application Data\Autodesk\<Product Version>` folder.

NOTE In some operating systems, the folders that are located under your profile are hidden by default. To display these files, you may need to change your display settings. On the Start menu, click Control Panel ► Folder Options. In the Folder Options dialog box, on the View tab, click Show Hidden Files and Folders.

Locate Plot Style Files

Beginning with AutoCAD LT 2004, the default location of your plot style files has changed. For information about the default location of these files, see Locate Customized Files on page 17.

NOTE In some operating systems, the folders that are located under your profile are hidden by default. To display these files, you may need to change your display settings. On the Start menu, click Control Panel ► Folder Options. In the Folder Options dialog box, on the View tab, click Show Hidden Files and Folders.

To locate your plot style files

- 1 Click Start menu (Windows) ► All Programs (or Programs) ► Autodesk ► AutoCAD LT 2009 ► AutoCAD LT 2009.
- 2 Click Tools menu ► Options.
- 3 In the Options dialog box, Files tab, click the plus sign (+) to the left of Printer Support File Path.
- 4 Click the plus sign (+) to the left of the Plot Style Table Search Path file.
- 5 Under Plot Style Table Search Path, click the path name to view the location of your plot style files.

NOTE You can also locate your plot style files by entering **stylesmanager** on the AutoCAD LT command line.

Locate Plotter Files

Beginning with AutoCAD LT 2004, the default location of your plotter files has changed. For information about the default location of these files, see Locate Customized Files on page 17.

NOTE In some operating systems, the folders that are located under your profile are hidden by default. To display these files, you may need to change your display settings. On the Start menu, click Control Panel ► Folder Options. In the Folder Options dialog box, on the View tab, click Show Hidden Files and Folders.

To locate your plotter files

- 1 Click Start menu (Windows) ► All Programs (or Programs) ► Autodesk ► AutoCAD LT 2009 ► AutoCAD LT 2009.
- 2 Click Tools menu ► Options.
- 3 In the Options dialog box, Files tab, click the plus sign (+) to the left of Printer Support File Path.
- 4 Click the plus sign (+) to the left of Printer Configuration Search Path.
- 5 Under Printer Configuration Search Path, click the path name to view the location of your plotter files.

NOTE You can also locate your plotter files by entering **plottermanager** on the AutoCAD LT command line.

Locate the PMP File

Beginning with AutoCAD LT 2004, the default location of your PMP file has changed. For information about the default location of this file, see *Locate Customized Files* on page 17.

NOTE In some operating systems, the folders that are located under your profile are hidden by default. To display these files, you may need to change your display settings. On the Start menu, click Control Panel ► Folder Options. In the Folder Options dialog box, on the View tab, click Show Hidden Files and Folders.

To locate your PMP file

- 1 Click Start menu (Windows) ► All Programs (or Programs) ► Autodesk ► AutoCAD LT 2009 ► AutoCAD LT 2009.
- 2 Click Tools menu ► Options.
- 3 In the Options dialog box, Files tab, click the plus sign (+) to the left of Printer Support File Path.

- 4 Under Printer Description File Search Path, click the path name to view the location of your PMP file.

Locate Support Files

Beginning with AutoCAD LT 2004, the default location for some of your support files has changed. For information about the default location of these files, see *Locate Customized Files* on page 17.

Support files include the following:

- Customization file (*acadlt.cui*)
- Custom icon files
- Help and miscellaneous files
- Font mapping file (*acadlt.fmp*)
- Alternate font file (*simplex.shx*)
- Support path files (*acadlt.dcl*, *acadlt.lin*, *acadlt.pat*, *acadlt.pgp*, *acadlt.psf*, *acadlt.unt*, *acadltiso.lin*, *acadltiso.pat*, and *gdt.shx*)

To find the default location of the customization files

- 1 Click Start menu (Windows) ► All Programs (or Programs) ► Autodesk ► AutoCAD LT 2009 ► AutoCAD LT 2009.
- 2 Click Tools menu ► Options.
- 3 In the Options dialog box, Files tab, click the plus sign (+) to the left of Customization Files.
- 4 Click the plus sign (+) to the left of Main Customization File.
- 5 Under Main Customization File, click the path name to view the location of your main customization file.
- 6 Click the plus sign (+) to the left of Enterprise Customization File.
- 7 Under Enterprise Customization File, click the path name to view the location of your enterprise customization files.

NOTE By default, the path to an enterprise customization file is empty until you define the file. For more information about defining a customization file, see “Customize the User Interface” in the *Customization Guide*.

To find the default location of the custom icon files

- 1 Click Start menu (Windows) ► All Programs (or Programs) ► Autodesk ► AutoCAD LT 2009 ► AutoCAD LT 2009.
- 2 Click Tools menu ► Options.
- 3 In the Options dialog box, Files tab, click the plus sign (+) to the left of Customization Files.
- 4 Under Custom Icon Location, click the path name to view the location for the custom button image files used with your customization files.

To find the default location of the Help and miscellaneous files

- 1 Click Start menu (Windows) ► All Programs (or Programs) ► Autodesk ► AutoCAD LT 2009 ► AutoCAD LT 2009.
- 2 Click Tools menu ► Options.
- 3 In the Options dialog box, Files tab, click the plus sign (+) to the left of Help and Miscellaneous File Names to expand the list.
- 4 Click the plus sign (+) to the left of the file you want to locate, and then click the path name to view the location of the files.

To find the default location of the font mapping file

- 1 Click Start menu (Windows) ► All Programs (or Programs) ► Autodesk ► AutoCAD LT 2009 ► AutoCAD LT 2009.
- 2 Click Tools menu ► Options.
- 3 In the Options dialog box, Files tab, click the plus sign (+) to the left of Text Editor, Dictionary, and Font File Names.
- 4 Click the plus sign (+) to the left of Font Mapping File.
- 5 Under Font Mapping File, click the path name to view the location of your font mapping file.

To find the default location of the alternate font file

- 1 Click Start menu (Windows) ► All Programs (or Programs) ► Autodesk ► AutoCAD LT 2009 ► AutoCAD LT 2009.
- 2 Click Tools menu ► Options.
- 3 In the Options dialog box, Files tab, click the plus sign (+) to the left of Text Editor, Dictionary, and Font File Names.
- 4 Click the plus sign (+) to the left of Alternate Font File.
- 5 Under Alternate Font File, click the path name to view the location of your alternate font file.

To find the default location of the support path files

- 1 Click Start menu (Windows) ► All Programs (or Programs) ► Autodesk ► AutoCAD LT 2009 ► AutoCAD LT 2009.
- 2 Click Tools menu ► Options.
- 3 In the Options dialog box, Files tab, click the plus sign (+) to the left of Support File Search Path.
- 4 Under Support File Search Path, click a path name to view the location of your support files.

Locate Drawing Template Files

Beginning with AutoCAD LT 2004, the default location of your drawing template files has changed. For information about the default location of these files, see *Locate Customized Files* on page 17.

NOTE In some operating systems, the folders that are located under your profile are hidden by default. To display these files, you may need to change your display settings. On the Start menu, click Control Panel ► Folder Options. In the Folder Options dialog box, on the View tab, click Show Hidden Files and Folders.

To locate your drawing template files

- 1 Click Start menu (Windows) ► All Programs (or Programs) ► Autodesk ► AutoCAD LT 2009 ► AutoCAD LT 2009.
- 2 Click Tools menu ► Options.

- 3 In the Options dialog box, Files tab, click the plus sign (+) to the left of Template Settings.
- 4 Under Template Settings, click the plus sign (+) to the left of Drawing Template File Location.
- 5 Under Drawing Template File Location, click the path name to view the location of your drawing template files.

Install Autodesk Products for an Individual User

3

This section provides instructions for installing and activating your Autodesk product(s) for an individual user on a stand-alone computer. For information about installing network-licensed or multi-seat stand-alone versions of the program, see the *Network Administrator's Guide*, located on the Documentation tab of the Installation wizard and in the Help system.

The AutoCAD LT 2009 Installation Wizard

The AutoCAD LT Installation Wizard contains all installation-related material in one place. From the Installation wizard, you can access user documentation, install the product and supplemental tools, view support solutions, and learn about deploying your product on a network.

- **Review installation documentation before you install.** You can access system requirements, the *AutoCAD LT Stand-Alone Installation Guide*, and the *Readme.chm* file before you install your product. Click the Read the Documentation link and click a document you want to view.

NOTE To view or print any files with an extension of *.pdf*, Adobe® Reader must be installed on your computer. If you do not have Adobe Reader, you can download the latest version by visiting www.adobe.com.

- **Install AutoCAD LT.** From the Installation wizard, click Install Products. Follow the on-screen instructions to complete the installation.

System Requirements

Before you install your product on a stand-alone computer, make sure that your computer meets the minimum system requirements.

Whether the Windows operating system is the 32-bit or the 64-bit version is automatically detected when installing AutoCAD LT. The appropriate version of AutoCAD LT will be installed. The 32-bit version of AutoCAD LT cannot be installed on a 64-bit version of Windows.

See the following table for hardware and software requirements.

Hardware and software requirements		
Hardware/Software	Requirement	Notes
Operating system	32-Bit Windows Vista Enterprise Windows Vista Business Windows Vista Ultimate Windows Vista Home Premium Windows XP Professional, Service Pack 2 Windows XP Home, Service Pack 2	It is recommended that non-English language versions of AutoCAD LT be installed on an operating system with a user interface language that matches the code page of the AutoCAD LT language. A code page provides support for character sets used in different languages.
	64-Bit Windows Vista Enterprise Windows Vista Business Windows Vista Ultimate Windows Vista Home Premium	
Web browser	32-bit Internet Explorer 6.0 SP1 or later 64-bit Internet Explorer 7.0 or later	You cannot install AutoCAD LT if Microsoft Internet Explorer 6.0 with Service Pack 1 (or later) is not installed on the installation workstation. You can download Internet Explorer from the Microsoft website: http://www.microsoft.com/downloads/
Processor	32-bit Intel® Pentium® 4 processor or AMD® Athlon, 2.2 GHz or greater or	

Hardware and software requirements

Hardware/Software	Requirement	Notes
	Intel or AMD Dual Core processor, 1.6 GHz or greater 64-bit AMD 64 or Intel EM64T	
RAM	32-bit 512 MB (Windows XP SP2) 1 GB (Windows Vista) 64-bit 2 GB	
Graphics card	1024 x 768 VGA with True Color	■ Requires a Windows-supported display adapter.
Hard disk	550 MB (32 and 64-bit)	
Pointing device	Mouse, trackball, or other device	
DVD/CD-ROM	Any speed (for installation only) 32-bit Download (ESD) and installation from DVD or CD-ROM 64-bit Download or DVD	
Optional hardware	Printer or plotter Digitizer Modem or access to an Internet connection Network interface card	

NOTE Adobe Flash Player is no longer installed by default. If a suitable version of Flash is not currently installed on your system, a message is displayed requesting that you download it from Adobe's website. If you do not have Internet access, you can also access the Flash installer on the AutoCAD LT product media.

Install AutoCAD LT

This section contains information for installing AutoCAD LT on a stand-alone computer. You must have administrative permissions to install AutoCAD.

To install AutoCAD LT using default values on a stand-alone computer

This is the fastest means of installing AutoCAD LT on your system. Only default values are used which means it is a typical installation being installed to *C:\Program Files\AutoCAD LT 2009*. The text editor defaults for Windows NotePad and Express Tools are included.

- 1 Insert the AutoCAD LT DVD, or the first CD, into your computer's drive.
- 2 In the AutoCAD LT Installation wizard, click Install Products.
- 3 Next, select the product(s) you want to install and click Next.

NOTE AutoCAD Design Review 2009 is not installed by default when you install AutoCAD. Some AutoCAD features require that Design Review be installed to work properly. Design Review is the replacement viewer for DWF Viewer. For more information about the affected features, see *Features that Require Design Review on page 35*


- 4 Review the Autodesk software license agreement for your country or region. You must accept this agreement to proceed with the installation. Choose your country or region, click I Accept, and then click Next.

NOTE If you do not agree to the terms of the license and want to terminate the installation, click Cancel.

- 5 On the Products and User Information page, enter your serial number and user information and click Next.

IMPORTANT The information you enter here is permanent and is displayed in the AutoCAD LT window (accessed by Menu browser ► Help ► About) on your computer. Because you can't change this information later without uninstalling the product, make sure you enter the correct information now.

- 6 If you do not wish to make configuration changes on the Review - Configure - Install page, select Install. Then select Yes, to continue installing using the default configuration.



The wizard does the following;

- Uses a Typical installation, which installs the most common application features. To see which features are included in a Typical installation, refer to Typically Installed Features on page 38.
- Includes the Express Tools library of productivity tools that extend the power of AutoCAD LT.
- Installs AutoCAD LT to the default install path of *C:\Program Files\AutoCAD LT 2009*.

7 Click Install.

To install AutoCAD LT using configured values on a stand-alone computer

With this installation method, you can fine-tune exactly what gets installed by using the Configure option. You can alter the installation type, the install path, license type, and the default text editor. You can also choose to install material libraries.

- 1 Insert the AutoCAD LT DVD, or the first CD, into your computer's drive.
- 2 In the AutoCAD LT Installation wizard, click Install Products.
- 3 Next, select the product(s) you want to install and click Next.
- 4 Review the Autodesk software license agreement for your country or region. You must accept this agreement to proceed with the installation. Choose your country or region, click I Accept, and then click Next.

NOTE If you do not agree to the terms of the license and want to terminate the installation, click Cancel.

- 5 On the Products and User Information page, enter your user information and click Next.

IMPORTANT The information you enter here is permanent and is displayed in the AutoCAD LT window (accessed by Menu browser ► Help ► About) on your computer. Because you can't change this information later without uninstalling the product, make sure you enter the correct information now.

- 6 On the Review - Configure - Install page, click Configure to make configuration changes such as installation type, installing optional tools, or changing the installation path.
- 7 On the Select the Installation Type page, you can choose to make the following configuration changes:
 - Typical - Installs the most common application features.
 - Custom - Installs only the application features that you select from the Select Features To Install list:

Dictionaries	Contains multi-language dictionaries.
--------------	---------------------------------------

Fonts	Contains AutoCAD fonts and True Type fonts.
-------	---

New Features Workshop	Contains animated demos, exercises, and sample files to help users learn the new features.
-----------------------	--

Portable License Utility	Contains portable license management tools.
--------------------------	---

Migrate Custom Settings	Migrates custom settings and files from a previous version of your product to this version. See Migrate Custom Settings on page 8.
-------------------------	--

Samples	Contains various feature sample files.
---------	--

- Product Install Path - Specifies the drive and location where AutoCAD LT will be installed.
- Create a Desktop Shortcut - Choose whether to display the AutoCAD LT shortcut icon on your desktop. A product icon is displayed on your

desktop by default. Clear the check box if you do not want to display the shortcut icon.

- 8 Click another product tab to configure another product, or Next and then Configuration Complete to return to the Review - Configure - Install page. Then, click Install.

NOTE If you want a printed copy of your configuration settings, click the Print button.

- 9 On the Installation Complete page, choose from the following:

View the installation log file If you want to view the installation log file, its location is displayed.

View the AutoCAD LT Readme The *Readme* file is opened from this page when you click Finish. This file contains information that was unavailable when the AutoCAD LT 2009 documentation was prepared. If you do not want to view the *Readme* file now, clear the check box next to Readme.

NOTE You can also view the *Readme* file after you have installed AutoCAD LT.

- 10 Click Finish.

You have successfully installed AutoCAD LT. You are now ready to register your product and start using the program. To register the product, start AutoCAD LT and follow the on-screen instructions.

NOTE Autodesk does not recommend or support the distribution of an Autodesk product using imaging software. However, if you plan to use this method of distribution, please review the instructions detailed in *Distribute the Product Using Imaging Software* in the *Network Administrator's Guide*.

Register and Activate AutoCAD LT

The first time you start AutoCAD LT, the Product Activation wizard is displayed. You can either activate AutoCAD LT at that time or run AutoCAD LT and activate it later. Until you register and enter a valid activation code for AutoCAD LT, you are operating the program in *trial mode* and the Product Activation wizard is displayed for 30 days from the first time that you run the program. If after 30 days of running AutoCAD LT in trial mode you have not

registered and provided a valid activation code, your only option is to register and activate AutoCAD LT. You will not be able to run in trial mode after the 30 days expires. Once you register and activate AutoCAD LT, the Product Activation wizard is no longer displayed.

The fastest and most reliable way to register and activate your product is by using the Internet. Simply enter your registration information and send it to Autodesk over the Internet. Once you submit your information, registration and activation occur almost instantly.

To register and activate AutoCAD LT

- 1 Click Start menu (Windows) ► All Programs (or Programs) ► Autodesk ► AutoCAD LT 2009 ► AutoCAD LT 2009.
- 2 In the AutoCAD LT 2009 Product Activation wizard, select Activate the Product, and then click Next.
This starts the Register Today process.
- 3 Click Register and Activate (Get an Activation Code).
- 4 Click Next and follow the on-screen instructions.

If you do not have Internet access, or if you want to use another method of registration, you can register and activate AutoCAD LT in one of the following ways:

Email Create an email message with your registration information and send it to Autodesk.

Fax or Post/Mail Enter your registration information, and fax or mail the information to Autodesk.

Add or Remove Features

You can add or remove AutoCAD LT features at any time. For example, you may have chosen a Custom installation option when you first installed AutoCAD LT, but now you want to add features that you did not install originally. Or you may no longer need to use all of the features that were installed originally. You can add or remove features by using the Add or Remove Programs dialog box.

To add or remove features

- 1 In the Control Panel (Windows), double-click Add or Remove Programs.
- 2 In the Add or Remove Programs dialog box, click AutoCAD LT 2009, and then click Change/Remove.
The AutoCAD LT Installation wizard re-opens in Maintenance Mode.
- 3 Click Add or Remove Features.
- 4 On the Add/Remove Features page, select a feature to install or uninstall. The icons to the left of the selections give you an indication of the action that will be taken.



Indicates a feature that was originally not installed.



Indicates a currently installed feature or a feature that you want to add.



Indicates an originally installed feature that is chosen for removal.

NOTE If you need to revert to the AutoCAD LT features that you selected in your original installation, click Cancel.

Click Next.

- 5 On the Update AutoCAD LT 2009 Installation page, click Next.
- 6 On the Update Complete page, you are informed when the updates have been performed. Click Finish.

Reinstall or Repair AutoCAD LT

If you accidentally delete or alter files that are required by AutoCAD LT, AutoCAD LT might not perform correctly, and you might receive error messages when you try to execute a command or find a file. You can attempt to fix this problem by reinstalling or repairing AutoCAD LT. The reinstallation or repair uses the features that were part of the installation type you chose when you initially installed the program.

To reinstall or repair AutoCAD LT

- 1 In the Control Panel (Windows), double-click Add or Remove Programs.
- 2 In the Add or Remove Programs window, select AutoCAD LT 2009, and then click Change/Remove.
The AutoCAD LT Installation wizard re-opens in Maintenance Mode.
- 3 Click Repair AutoCAD LT 2009.
- 4 On the Select Repair or Reinstall page, click one of the following, and then click Next:
 - **Repair My AutoCAD LT 2009 Installation.** This option replaces all registry entries that AutoCAD LT initially installed and restores AutoCAD LT 2009 to its default state. If you are missing AutoCAD LT files, use this option.
 - **Reinstall My AutoCAD LT 2009 Installation.** This option repairs the registry and reinstalls all files from the original installation. Use this option if the Repair My AutoCAD LT 2009 Installation option does not solve the problem.
- 5 On the Repair AutoCAD LT 2009 page, click Next to start the process.
- 6 On the Repair Complete page, you are informed when the repairs have been performed. Click Finish.

Uninstall AutoCAD LT

When you uninstall AutoCAD LT, all components are removed. This means that even if you've previously added or removed components, or if you've reinstalled or repaired AutoCAD LT, the uninstall removes all AutoCAD LT installation files from your system.

To uninstall AutoCAD LT

- 1 In the Control Panel (Windows), click Add or Remove Programs.
- 2 In the Add or Remove Programs window, select AutoCAD LT 2009, and then click Change/Remove.
- 3 Click Uninstall.

- 4 On the Uninstall AutoCAD LT 2009 page, click Next to remove AutoCAD LT from the system.
- 5 When informed that the product has been successfully uninstalled, click Finish.

NOTE Even though AutoCAD LT is removed from your system, the software license remains. If you reinstall AutoCAD LT at some future time, you will not have to register and re-activate the program.

Features that Require Design Review

Design Review is a tool for reviewing and working with DWF files. DWF files are drawing files that have been converted so they can be transported over the Internet and then shared with others. In order to work with DWF files, you need to have Design Review installed.

If you want to use any of the following commands or functions with a DWF file, you need to have Design Review installed.

- PUBLISH
- PLOT
- PUBLISH TO WEB
- EXPORT
- MARKUP
- AUTOPUBLISH

Installation Troubleshooting

4

This chapter provides solutions to installation issues and answers to commonly asked questions that may arise while installing your product(s).

General Installation Issues

This section outlines common issues and their solutions that may arise while performing a general install of your product(s).

How can I check my graphics card driver to see if it needs to be updated?

It is recommended that you verify and update your graphics card driver to optimize your program. Use the following procedure to identify your current graphics card driver.

To identify your graphics card driver

- 1 On the Start menu (Windows), click Settings ► Control Panel.
- 2 Click the Display icon to access the Display Properties.
In Vista, click Settings ► Control Panel ► Personalization ► Display Settings.
- 3 Open the Settings tab and click the Advanced button.
- 4 Click the Adapter tab to check the adapter type.

- 5 Click the Properties button and open the Driver tab to check driver version and see if newer drivers are available.

TIP Many newer graphic cards offer tabbed pages where you can learn more precise information about your specific graphic card. If specific tab pages are present, refer to them instead of the Adapter tab.

What is the text editor used for?

The text editor you designate during installation is used for editing text files such as PGP and CUS dictionary files while you are running your product.

When performing a Typical installation, what gets installed?

A Typical installation includes the following features:

Dictionaries	Contains multilanguage dictionaries.
Fonts	Contains program fonts. (True Type fonts are automatically installed with the program.)
New Features Workshop	Contains animated demos, exercises, and sample files to help users learn new features.
Portable License Utility	Contains a tool for moving a stand-alone license between computers.
Migrate Custom Settings	Allows you to migrate custom settings and files from previous releases. For more information, see Migrate Custom Settings on page 8.
Samples	Contains various feature sample files.

Where are my product manuals?

All documentation created for Autodesk products are built in two different formats: PDF and CHM.

- PDF files are made available during installation; click the Documentation link in the installer.
- CHM files are available after the product is installed; they are accessed in the Help system in the product.

The entire content of the PDF files are available from within your installed product's Help system.

Files are also installed to the `\AutoCAD LT\Help` folder.

Deployment Issues

This section outlines common issues and their solutions with regards to software deployments.


Is there a checklist I can refer to when performing a deployment?

The *Network Administrator Guide* contains a complete section that describes preliminary actions and the entire deployment process. See Preliminary Tasks for a Network Deployment.

Where should deployments be located?

Shared folders are required for both network license and multi-seat stand-alone methods of installation. The shared folder (*network share*) is created before you run the Installation wizard and is where product deployments are stored.

It is recommended that you name the network share folder *Deployments* on the desktop of the system where you want deployments stored. You can then add subfolders inside the shared *Deployments* folder that clearly convey the names of products you plan to deploy. For example:



Any subfolders that are placed inside a shared folder are automatically shared.

TIP You must have Full Control permissions set for your shared folder when you are creating your deployment images. Read permissions are necessary to access the network share and administrative permissions on the workstation where the program is deployed.

Where can I check if service packs are available for my software?

To find out if a patch or Service Pack is available for your product, visit the Autodesk Product Support page at <http://support.autodesk.com/>.

How do I extract an MSP file?

A Microsoft Patch (MSP) file is usually contained in a Service Pack executable that you download from the Autodesk Product Support website. To extract the MSP file from the executable, run the patch program from the Windows command prompt using the `/e` switch.

Pay particular attention to the location where the files are extracted. For details about using the patch file, review the *Readme* file for that patch.

Can Online Resource settings be modified later?

Yes. If you want to change the state of online resources after a product is installed, you can do that from the CAD Manager Control utility. The CAD Manager Control utility is installed separately from AutoCAD LT.

From the Installation wizard, select Install Tools and Utilities and then select the CAD Manager Control utility. After installation is complete, you can start the utility from the Start menu (Windows). Click All Programs (or Programs) > Autodesk > CAD Manager Tools > CAD Manager Control Utility.

Where can I learn about InfoCenter?

You can use InfoCenter to enter a question for help, display the Communication Center panel for product updates and announcements, or display the Favorites panel to access saved topics. For more information, refer to Search For and Receive Information.

What are information channels?

The Communication Center component of InfoCenter allows you to receive announcements from various information channels. Through information channels, you can receive the following:

- Product Support information, including maintenance patch notifications.
- Subscription Center announcements and subscription program news, as well as links to e-Learning Lessons, if you are an Autodesk subscription member.
- Notifications of new articles and tips posted on Autodesk websites.

What are the benefits to enabling CAD Manager Channels?

CAD Manager Channels allow access to Internet-based content and information feeds from a specified feed location.

What are RSS feeds and how do they benefit my installation?

An RSS feed is a live link you initiate by subscribing to someone's website. Once subscribed, the primary benefit is a constantly updating stream of content that is delivered to your system in the form of summarized articles, forum threads, blog posts, and so on. RSS stands for Rich Site Summary (or Really Simple Syndication).

Where can I learn about InfoCenter search locations?

You can use InfoCenter to search multiple sources (for example, Help and specified files) at one time, or choose to search a single file or location.

For more information, refer to Search for Information.

How do I set or customize search locations?

InfoCenter Search and Communication Center settings can be set in the InfoCenter Settings dialog box or in the CAD Manager Control utility. You must use the CAD Manager Control utility to specify CAD Manager Channel settings.

See Specify InfoCenter Settings for more information regarding the settings you can configure.

Licensing Issues

This section outlines common issues and their solutions with regards to software licenses and licensing your product(s).

What is the difference between a stand-alone license and a network license?

Stand-alone licensed products are registered and activated to an individual workstation. While the software can be installed on multiple systems in your facility, the license only allows one system to be operational. The Portable License Utility can be used if a license needs to be transferred to another system. If you need to run more systems, you need to purchase more stand-alone licensed products, or consider converting to *multi-seat stand-alone* licenses.

You cannot purchase a network licensed version of AutoCAD LT. However, a multi-seat stand-alone licensed version is available that does not rely upon servers to maintain licenses. Multi-seat stand-alone licensing means that each installation of your product uses a single serial number for registration and activation.

What is the benefit to using a network licensed version of the software?

Since a network license option is not available for AutoCAD LT, a multi-seat stand-alone license is recommended for large drafting/design facilities, classrooms, and lab environments. Unlike a network licensed product, you can install multi-seat stand-alone products on the maximum number of systems that the license allows. For example, you purchase a multi-seat stand-alone license for 25 seats and have 30 systems at your facility that can communicate over the Internet. Even though you can install software on all 30 systems, only the first 25 systems you start will have their licenses activated. Because the licenses are tied to each specific system, the remaining five systems will never be able to run the software unless you purchase an additional five licenses.

As long as all the systems have Internet access, products are automatically activated the first time they are launched.

What is Internet Explorer used for?

After installing your product, you can operate in *trial mode* for a given number of days. Whenever you launch the program, you are prompted to activate the

software. When you choose to activate the software, Internet Explorer makes this process much faster. Once you entered your registration data and submit it to Autodesk, an activation code is returned and you are not prompted again during startup.

Networking Issues

This section outlines common issues and their solutions with regards to performing a network installation or configuring your network license server(s).

When installing tools and utilities, which selections are applicable for a multi-seat stand-alone installation?

Since a multi-seat stand-alone licensed product does not rely upon a license server to manage or activate the license, the only tool that is beneficial is the Autodesk CAD Manager tool.

You need the CAD Manager tool if you want to make changes to CAD Manager Channels.

When installing tools and utilities, which selections are applicable for a stand-alone installation?

The Autodesk CAD Manager tool is the only tool that is beneficial to a stand-alone licensed product. With the CAD Manager tool, you can modify CAD Manager Channels.

If I choose to create a log file, what kind of information does the log file contain?

There are two types of log files that can be generated that monitor information about deployments and installations.

The Network log file keeps a record of all workstations that run the deployment. The log lists the user name, workstation name, and the status of the installation. Refer to this file for status information and details about problems that users may have encountered during installation.

The Client log file contains detailed installation information for each workstation. This information may be useful in diagnosing installation problems. The client log is located in the `\Temp` directory of each client workstation.

When specifying user workstation settings, I'm given the option to specify a profile. What are profiles?

Profiles are created on the Profiles tab of the Options dialog box. Profiles can contain configuration settings for just about anything that is not a drawing based system variable. For example, a profile can contain things like support paths, grip settings, and plot settings.

When you specify a profile on the Specify User Preferences page during the deployment process, it ensures that all workstations that use that deployment to install the product will be configured the same way.

Can I create custom desktop shortcuts?

You can choose to create custom desktop shortcuts that use command line switches to specify several options when you start the program. For example, command line switches can be set to run a script during program launch, create a drawing based on a template or prototype drawing, or designate a workspace that should be restored on startup.

For more information, see [Customize Startup](#).

What happens when you choose to append or merge service packs?

When you append a service pack, the service pack is applied to the current deployment only. Multiple service packs may be appended to a deployment. The service pack file is included in the deployment and the service pack is applied after the product is deployed.

When you merge a service pack, the service pack is merged into the administrative image. Once merged, a service pack may not be removed from the administrative image. Multiple service packs may be included in a single administrative image.

You can choose to append or merge service packs from the Include Service Packs page when creating a deployment.

What is an administrative image (MSI) file?

An *administrative image* is a collection of shared file resources created during the deployment process and is used by deployments to install the program to networked workstations. Service packs (patches) can be applied to an administrative image when you create the deployment. A *.msi* file is a Microsoft Installer file.

What is the impact of selecting all products to be included in the administrative image?

If you elect to include all products in your deployment, the administrative image will be larger. You should select all products only when you create multiple deployments from this image and prefer not to use the installation disk. If there are products you rarely or never use, and you do not expect to create additional deployments, you should only select a subset of products.

You can still create a deployment at a later date, and include additional products, but you need to create a new administrative image. You need the installation media to do so.

Uninstall and Maintenance Issues

This section outlines common issues and their solutions with regards to adding and removing features, reinstalling or repairing your installation, and uninstalling products.

When adding or removing features, how can I tell what features get installed by default?

To quickly see what gets installed during a typical, default installation, click the Restore Defaults button on the Add/Remove Features page.

Dictionaries	Contains multilanguage dictionaries.
Fonts	Contains program fonts. (True Type fonts are automatically installed with the program.)
New Features Workshop	Contains animated demos, exercises, and sample files to help users learn new features.
Portable License Utility	Contains a tool for moving a stand-alone license between computers.
Migrate Custom Settings	Allows you to migrate custom settings and files from previous releases. For more information, see Migrate Custom Settings on page 8.
Samples	Contains various feature sample files.

Is it possible to change the installation folder when adding or removing features?

Once your product is installed, you cannot change the installation path from the Add/Remove Features page. Changing the path while adding features results in program corruption, so it is not an option.

When should I reinstall the product instead of a repair?

You should reinstall your product if you accidentally delete or alter files that are required by the program. Missing or altered files adversely affect the performance of your product and cause error messages when you try to execute a command or find a file.

If an attempt to repair an installation fails, reinstalling is the next best option.

Do I need my original disk to reinstall my software?

When performing a reinstall of the product, you do not need to have the original DVD or CD on hand. Installation data is cached locally on your drive and that data is reused when reinstalling.

After repairing my installation, is it possible to recover my settings?

Custom settings can be exported and later re-imported to the same system in case you have to repair the installation of your program.

For more detailed information regarding exporting and importing custom settings, see [Export and Import Custom Settings from the Same Release](#) on page 13.

When I uninstall my software, what files are left on my system?

If you uninstall the product, some files remain on your system such as files you created or edited (drawings or custom menus).

Your license file also stays on your workstation when you uninstall your product. If you reinstall on the same workstation, the license information remains valid and you do not have to reactivate the product.

Index

A

- activating programs 4, 31
- administrator permission requirements 2
 - stand-alone installation 2
- aliases 8
 - migrating 8
- alternate font mapping files 20
- anti-virus software 3
- applications 3
 - anti-virus software 3
 - closing during installation 3
- AutoCAD 7, 39
 - product manuals 39
 - versions of 7
- Autodesk Design Review 35
 - features requiring 35

B

- browsers 26
- bundled products 2

C

- CAD Manager Control utility 5
 - installing 5
- computers 26
- converting 8
 - menu files to CUI format 8
- CUI (customization) files 8
- custom icon files 20
- custom settings 3, 7, 13, 15–16
 - exporting to other systems 13, 15
 - importing migration packages 13, 16
 - migrating from previous releases 3, 7
- customization files (CUI) 8, 20
 - locating files 20
 - migrating older menu files to 8

- customizing 7, 13, 17, 32
 - installation 32
 - locating customized files 17
 - migrating older customization files 7
 - migration packages 13
 - types of customized files 17

D

- data loss 3
- displaying 12, 18
 - hidden files 18
 - migration log files 12
- downloading 7
 - migration tools 7
- drawing templates 22
 - locating files 22
- DWG TrueView migration tool 13
- DWT files 22
 - locating 22

E

- email registration 32
- exporting 13, 15
 - custom settings as migration packages 13, 15

F

- faxing registration information 32
- files 13, 15–17
 - custom settings files 13
 - locations 17
 - migration packages 13
 - network locations 15–16
 - roaming profiles and 17
- finding 17
 - customized files 17
- FMP files (font mapping) 20

font mapping files 20

H

hard disks 26
 system requirements 26
hardware 1, 26
 installation requirements 1, 26
hatches 8
 migrating patterns to new releases 8
Help 20
 locating Help files 20
hidden files 18

I

importing 13, 16
 custom settings from migration
 packages 13, 16
installation 1–2, 4–5, 7, 25–26, 31–34,
 37–39, 42, 44, 46
 adding or removing features 32
 CAD Manager Control utility 5
 Installation wizard 25
 licensing 42
 multiple or bundled products 2
 networking issues 44
 preparing for 1
 registration and activation 4, 31
 reinstalling 33
 serial numbers 2
 side-by-side 7
 software deployments 39
 stand-alone installation 1, 25
 starting AutoCAD 4
 system requirements 26
 troubleshooting 37
 typical 38
 uninstalling 34, 46
Installation wizard 25
interface 8
 migrating custom settings for 8
Internet 31
 program registration and
 activation 31
Internet Explorer (Microsoft) 26

L

legacy menu files 8
licenses 42
 issues 42
LIN files (linetype library) 8, 20
linetypes 8
 migrating to new releases 8
log files 12
 migration log files 12

M

mailing registration information 32
memory (RAM) 26
 system requirements 26
menus 8
 migrating to new releases 8
Microsoft Internet Explorer 26
Microsoft Windows operating
 systems 26
migrating 3, 7, 12–13
 custom settings from previous
 releases 3, 7
 migration log files 12
 migration packages 13
 migration tools 12
migration log file 12
migration packages 13
migration tools 12
MNS files (source menu) 8
 migrating 8
MNU files (menu template) 8
 migrating 8
monitors 26
multi-product bundles 2
multi-seat stand-alone installations 1

N

network installations 44
 issues 44
networks 15–16
 custom files located on 15–16

O

OpenGL driver 26
operating systems 26
 system requirements 26

P

PAT files 8, 20
PC3 files (plotter configuration) 8
 migrating 8
permission requirements 2
 stand-alone installation 2
PGP files (program parameters) 8, 20
plot styles 18
 locating files 18
plotter configuration files 18
 locating files 18
PMP files (plot model parameter) 19
pointing devices 26
 system requirements 26
previous releases 3, 7
 migrating custom settings from 3, 7
processors 26
Product Activation wizard 4, 31
profiles (user) 8
 migrating custom settings 8
PSF files 20

R

RAM 26
 system requirements 26
registering programs 4, 31
reinstalling programs 33
removing 32, 34
 program features 32
 uninstalling programs 34
repairing 33
 damaged installations 33

S

serial numbers 2
 stand-alone installation 2
service packs 26
side-by-side installation 7
software deployments 39
software installation requirements 26
stand-alone installations 1, 28, 31
 process 28
 program registration and activation 31
 Quick Start 1
starting 4
 AutoCAD 4
support files 20
 locations 20
system requirements 1, 26
 stand-alone installations 1, 26

T

templates 22
 locating files 22
tools 7, 12
 migration tools 7, 12
troubleshooting installation 37

U

uninstalling programs 34, 46
UNT files 20
upgrading 3
 installing newer AutoCAD releases 3
user interface 8
 migrating custom settings for 8

V

video cards 26
video monitors 26
virus software 3

W

web browsers 26

Windows operating systems 26
system requirements 26